



# NiCE

---

## 无法接管：解决方案指南

[https://kb-cn-stage.netapp.com/on-prem/ontap/Ontap\\_OS/OS-KBs/Takeover\\_not\\_possible\\_resolution\\_...](https://kb-cn-stage.netapp.com/on-prem/ontap/Ontap_OS/OS-KBs/Takeover_not_possible_resolution_...)

Updated: Wed, 03 Jun 2026 22:36:23 GMT

### 适用场景

- ONTAP 9
- MetroCluster IP解决方案除外

### 问题描述

[如果这会影响您的系统、请检查Active IQ](#)

无法执行接管、如错误消息中所示：

```
::> storage failover show -node ClusterA-01 -fields possible
node           possible
-----
ClusterA-01   false
```

### 发生原因

按照此解决方法指南、根据导致禁用接管的原因找到解决方案。

---

'NetApp provides no representations or warranties regarding the accuracy or reliability or serviceability of any information or recommendations provided in this publication or with respect to any results that may be obtained by the use of the information or observance of any recommendations provided herein. The information in this document is distributed AS IS and the use of this information or the implementation of any recommendations or techniques herein is a customers responsibility and depends on the customers ability to evaluate and integrate them into the customers operational environment. This document and the information

运行storage故障转移命令以确定原因：

```
::>storage failover show -instance -node <node_name>
```

示例：

```
::> storage failover show -instance
```

```
Node: cluster1-01
Partner Name: cluster1-02
Node NVRAM ID: 5#####
Partner NVRAM ID: 5#####
Takeover Enabled: true
HA Mode: ha
```

```
Takeover Possible: false
```

```
Reason Takeover not Possible: Local node missing partner disks
```

## 解决方案



ONTAP Select

AF/ FAS

## ► 单击以查看表格格式的解决方案

消息

解决方案

操作员正在禁用接管

[无法接管：操作员正在禁用接管](#)

已禁用存储故障转移

[无法接管：HA对中的两个节点均未加入集群](#)

版本不匹配

[无法接管：版本不匹配](#)

降级模式(邮箱磁盘)

[无法接管：降级模式\(邮箱磁盘\)](#)

互连错误

[无法接管：互连错误](#)

磁盘架过热

[无法接管：磁盘架过热](#)

NVRAM 日志未同步

[无法接管：NVRAM日志未同步](#)

禁用接管后、配对节点已暂停

[无法接管：禁用接管后配对节点已暂停](#)

本地节点已处于接管状态

[无法接管：本地节点已处于接管状态](#)

本地节点即将暂停

[无法接管：本地节点即将暂停](#)

邮箱磁盘运行不正常

[无法接管：邮箱磁盘运行不正常](#)

HA互连已关闭

[无法接管：ONTAP Select : cf\\_diskInventory\\_sendFaffed Reason="HA互连已关闭"](#)

本地节点缺少配对磁盘

- [无法接管：本地节点在ONTAP Select中缺少配对磁盘](#)
- [无法接管：本地节点在CVO中缺少配对磁盘](#)
- [无法接管：本地节点在AFF或FAS中缺少配对磁盘](#)
  - ["无法接管"警报：由于磁盘出现故障、本地节点缺少磁盘](#)

## 追加信息

不适用